



IPAManager Quick Installation Guide

Windows setup installation and immediate post-installation validation

Scope - This guide covers only how to install the Windows setup package and what to verify immediately after installation.

1. Supported operating systems

The Windows installer is intended for supported x64 editions of the following operating systems.

- Windows 11 x64
- Windows Server 2025 x64
- Windows Server 2022 x64
- Windows Server 2019 x64
- Windows Server 2016 x64

2. Install the package

Download the setup EXE package to the target server, launch the installer, and complete the setup wizard.

3. Initial administrator access

After installation, sign in with the default administrator account below and change the password immediately after first login.

Username	Password
admin	changeme

Important - Replace the default password immediately and store the new credential securely.

4. Post-installation checks

- Confirm the IPAManager service is active.
- Confirm the application data directory exists under C:\ProgramData\IPAManager.
- Open the application URL (<http://<IP> /<HOSTNAME>>) in a browser and verify that the login page loads successfully.
- Sign in with the default administrator account and confirm that the dashboard opens without errors.
- Change the administrator password after first login.

5. Troubleshooting quick checks

- If the installer does not finish cleanly, rerun it as Administrator and review the setup log.
- If the service does not start, verify that installation completed successfully and review the Windows Event Viewer and service status output.
- If the web interface does not load, verify the IPAManager service, the IIS site state, and the configured binding or port.
- If the application opens but runtime data is missing, verify that C:\ProgramData\IPAManager exists and is writable by the service account.

This quick guide is intended for initial deployment validation only.